




JUICY GO

MORE
BOTHERSOME
BETTER PICTURES,
LOADS OF ADS

ALIENS

paparazzi!

Tales of Tinseltown

MANUAL

ACTIVISION®

EXCLUS
THE



Hints Revealed!

If you've read the hints
at the end of this manual
and still need help....

In the U.S. just dial:
1 (900) 680-HINT*
(\$.95 per min.)

In Canada call:
1 (900) 451-4849*
(\$1.25 per min.)

* Must be 18 years or older, or have a parent's
permission to call. Touch-tone only. Prices
subject to change without notice.



TABLE OF CONTENTS

Paparazzi! for Windows®	2
Minimum System Requirements	2
Installation	2
Starting Your Adventure in Tinseltown!	4
Tips for Running in Windows	4
Troubleshooting	6
Paparazzi! for Macintosh®	7
Minimum System Requirements	7
Installation	8
Starting Your Adventure in Tinseltown!	9
Tips for Running on the Macintosh	9
Troubleshooting	13
Customer Service	18
Here's the Scenario	19
Stalking the Prey with the Fabulous Palminator 2000	20
It's Time to Go on Star-Safari	22
It's Big Money Time	23
Ah, in Tinseltown at last	23
A Celebrity Seeker's Tour Guide	25
Credits	39
Hints	45

PAPARAZZI! FOR WINDOWS®

Minimum System Requirements

- IBM PC or 100% compatible
- 486DX-33 MHz
- 8 MB RAM
- Double-speed CD-ROM drive (300K/sec transfer rate)
- Hard disk drive with 22 MB available
- 256 color SVGA (640 x 480)
- MS-DOS or PC-DOS 6.0
- Microsoft® Windows 3.1 (Windows 95 compatible; NT not supported)
- Mouse
- 100% Windows compatible sound card

Installation

Windows 3.1

1. Insert DISC ONE into your CD-ROM drive. (We will assume this is your D drive.)
2. In Windows, drag down the FILE menu and select RUN. Then click the BROWSE button. Under the DRIVES section, go to drive D: or the drive letter which represents your CD-ROM drive. Double-click on SETUP.EXE and click the OK button in the RUN dialog box. Now follow the on-screen instructions to complete the installation.
3. When installation of Paparazzi! is complete, you must install **Quick-Time™ 2.0.1.41 for Windows** if you have an older version. Open

the folder QTW on your CD-ROM drive (which you chose in step 2). Double-click on SETUP.EXE and click the OK button in the RUN dialog box. Select LOCAL and click on CONTINUE. This installer will automatically install QuickTime™ and ask if you want to erase obsolete versions of QuickTime™. If you do have an older version, click REMOVE to erase it. Follow the on-screen instructions to complete the installation.

Windows 95

1. Insert DISC ONE into your CD-ROM drive. (We will assume this is your D drive.)
2. In Windows 95, click on the START menu button and click on RUN. Then click the BROWSE button. Find and double-click on the drive letter which represents your CD-ROM drive. Double-click on the SETUP program and click the OK button in the RUN dialog box. Now follow the on-screen instructions to complete the installation.
3. When installation of Paparazzi! is complete, you must install **QuickTime™ 2.0.1.41 for Windows** if you have an older version. To do this, click on the START menu button and then click on RUN. Now click the BROWSE button. Find and double-click on the drive letter which represents your CD-ROM drive. Open the folder QTW by double-clicking on it. Then double-click on the SETUP program and click OK in the RUN dialog box. Select LOCAL and click CONTINUE. Now follow the on-screen instructions to complete the installation.

Check out the READ ME file in the Museworthy program group for more performance and installation tips.

Starting Your Adventure in Tinseltown!

In Windows 3.1, look for the Museworthy program group on your desktop. Double-click to open it. Inside you'll find the PAPARAZZI! icon and the READ ME file. Double-click PAPARAZZI! and you're on your way!

In Windows 95, click the Start button, point to Programs, point to the Museworthy folder, then click on Paparazzi! to run the game. Now, you're on your way!

DO NOT launch the game off of your CD-ROM drive.

Tips for Running in Windows

If you suffer video performance lags, check your Windows manual for instructions on optimizing memory for CD-ROM playback. Each system is a little different, so please check the manuals that came with your computer before tearing apart your system. Be sure to save a copy of your original startup files. Keep in mind that most of these tips are geared for Windows 3.1 users.

Beyond that, here are some other things you can try:

1. Make sure no other programs are running.
2. In the SETTINGS... menu of the Windows Program Manager, turn "Minimize On Use" ON.
3. Disable any extraneous sounds you may have added to Windows. They take up RAM.
4. Disable any extra fonts you don't need.

5. Use MEMMAKER from the DOS prompt and free up as much extended memory as possible. Try turning Expanded (XMS) memory OFF. The Custom Settings of MEMMAKER will also allow you to optimize upper memory for Windows.
6. Get a CD-ROM disk caching utility. These are often more effective than SPEEDRV for CD-ROMs. We used Norton Speedrive. There are other good ones available from your local computer store or software catalog.
7. In the Buffers line of CONFIG.SYS, set BUFFERS to 10 or less.
8. Go through your CONFIG.SYS and AUTOEXEC.BAT files and REM out unnecessary drivers. If you find a really good configuration for Paparazzi! that is not so good for your other applications, make a boot disk with your Paparazzi! start-up settings on it, and boot from there when you play.
9. If you want to make more room on your hard drive, but still want to continue your Paparazzi! games at a later time, save ONLY the .TXT files in \MUSE_PC to another location or a floppy, then delete the entire \MUSE_PC directory. When you want to play again, install the game like always, then copy your saved .TXT files over the ones in the new \MUSE_PC directory.
10. Paparazzi! does not support Novell DOS 7, any shareware Windows shell or third-party memory caching utilities. Our suggestion is to run a nice, clean version of DOS/Windows 3.1 or Windows 95.
11. The video in Paparazzi! is optimized for 32,000 (or so) colors. Run your video card in 16-bit resolution for the best possible movie playback quality. You can try going down to 256 colors (8-bit) playback if 16-bit doesn't work.

Troubleshooting

Problem: My QuickTime™ movies just show a line or are not appearing.

Solution: You might not have the latest driver for your video card, which it needs to support QuickTime™. Contact your video card or computer manufacturer for the latest driver for your video card. Free driver updates are usually available via most on-line services or via mail.

Problem: What about driver compatibilities?

Solution: If you have one of the new local bus video cards that uses the Tseng4000 chipset, the newest driver will work. STB's SuperPixel Driver up to version 2.3 is not compatible. Also, check the QuickTime™ for Windows READ ME for sound and video card compatibility lists. Only change your driver as a last resort, try simpler memory management techniques first.

Problem: Load time for game start-up seems long. (1.5 to 2 minutes)

Solution: Paparazzi! prefers a CD-ROM drive named "D:\:". It will run on any drive letter, but it prefers D. If your CD-ROM drive letter is not D, you have either changed it, or there are other devices in your setup calling themselves "D."

If no other devices use D, here's how to change your CD-ROM drive to D:

1. Go into the AUTOEXEC.BAT startup file using EDIT.
2. Find the line that contains "MSCDEX". This is the CD-ROM driver.
3. Right at the end of the line, leave one space, then type /L:D.

Problem: A system error appeared on the screen while I was playing the game.

Solution: The first thing to do is not panic! The game automatically saves your progress (your progress is saved every time you come back from a shoot). These errors do surface from time to time because each computer is configured differently and certain conflicts do arise. Just quit out of the program and restart your computer. Restart Paparazzi! and choose the persona you were playing. You'll be back where you left off.

Please refer to the **READ ME** file in the Museworthy program group for additional troubleshooting information.

PAPARAZZI! FOR MACINTOSH

Minimum System Requirements

- 4400K of available memory (4096K for Paparazzi! and 300K for QuickTime™ overhead).
- 22 MB of available hard disk space
- A 68040 or PowerPC processor
- QuickTime 2.0 Apple Multimedia Tuner and QuickTime Musical Instruments (and QuickTime PowerPlug for PowerPCs). These extensions are available on Disc One
- A double-speed CD-ROM drive (300K/sec transfer rate)
- System 7.1.2 to 7.5 supported
- 640 X 480 – 256 (8-bit) color video
- 13" color monitor

Installation

1. Insert Disc One into your CD-ROM drive.
2. Open the Disc One “PPrazzi 1” CD and select the “MUSEWTHY” folder and drag it directly onto your hard drive. (Note: never run the program directly off of the CD and do not put the “MUSEWTHY” folder inside of another. It must remain on the top level of the hard drive.)

ALWAYS leave the “MUSEWTHY” folder as is. You can move the folder around the desktop, but do not move any of the items inside of the folder as there are hidden files in the folder that the game needs to run properly.

3. **If you are installing onto a PowerPC** — open the folder “Put in PowerPC System,” select and drag one item at a time into the System folder (the computer will place these files into the “Extensions” folder automatically). If you see any messages which you don’t understand, see the *Troubleshooting* section.

If you are installing onto a 680x0 Mac — open the folder “Put in 680x0 System,” select and drag one item at a time into the System folder (the computer will place these files into the “Extensions” folder automatically). If you see any messages which you don’t understand, see the first item in the *Troubleshooting* section.

4. Restart your computer (to enable the recently installed extensions you just placed in the System folder).

Starting Your Adventure in Tinseltown!

1. Insert Disc One into your CD-ROM drive.
2. Open the “MUSEWTHY” folder on your hard drive and double-click on the Paparazzi! icon. For some clues on how to become a successful paparazzi, see the *Here’s the Scenario* section. If you experience any problems with installation or while playing the game, see the *Tips for Running on the Macintosh* and *Troubleshooting* sections.

Tips for Running on the Macintosh

To get Paparazzi! to run optimally, perform these steps:

1. Set the Monitors control panel (in the Control Panels folder) to thousands of colors (16-bit). Paparazzi! is optimized for thousands of colors (16-bit), but if there are problems with the program, try switching to 256 colors (8-bit) as the program will run fine in this mode as well (the video will not be as detailed).
2. Turn off file sharing. This is accomplished by going into the Control Panels folder (located in the System folder) and double-clicking on Sharing Setup. Under the File Sharing section, make sure File Sharing is OFF. If it is not off, hit the Stop button to turn it off.
3. Turn off AppleTalk. This is accomplished by going into the Chooser (located in the Apple Menu) and hitting the Inactive button in the AppleTalk section.

4. In the Memory control panel, make sure Virtual Memory is OFF, Modern Memory Manager is ON and 32-Bit Addressing is ON (depending on the type of computer you have, not all of these options will be available). Restart your computer so that any changes you make will take effect.
5. As stated in the Minimum System Requirements section, approximately 4400K is needed in order to run the program (4096K for Paparazzi! and 300K for QuickTime™ overhead).

If your computer has more than 4400K of available memory (total memory minus system software and other opened programs) allocate as much as you can to Paparazzi! while leaving approximately 300K for QuickTime™ overhead. Once you have determined how much more memory you can allocate, type this number in the Preferred size field in the Get Info window of the Paparazzi! program icon. This is accomplished by selecting the Paparazzi! icon and getting info on it (either by choosing the option Get Info under the File menu or by hitting the Command and letter “I” keys simultaneously). Once in the Get Info window, click on the locked square (the “X” should disappear indicating that it is okay to change the number), change the number in the Preferred size field and then lock the window by clicking on the locked square. Close the Get Info window and now try playing Paparazzi!

6. If your computer has less than 4400K of available memory, you will need to make more memory available by performing one or more of the following steps:
 - A. Close any other programs which are currently open.

- B. Configure your system so less extensions (which use up memory) are being used by turning off any unnecessary extensions. (You need to leave ON the extensions which you put into your System folder in step 3 of the Installation section. You will also need to leave on any other extensions which will enable your CD-ROM drive to run properly.) This is accomplished by performing one of the following steps:
- If your system software is earlier than System 7.5 or doesn't have Extensions Manager — go into the “Extensions” folder and remove any unnecessary extensions by placing them in a different folder. (You may want to label this folder as “Disabled Extensions”.) Restart your computer for the changes to take effect. (This will disable the extensions you just placed in the “Disabled Extensions” folder.)

Once you are done playing Paparazzi!, open the “Disabled Extensions” folder drag the extensions inside back into the “Extensions” folder, and restart your computer. Your Macintosh is back to “normal” and you are now ready to run programs other than Paparazzi!

- If you have System 7.5 — you can use Extensions Manager. This is accomplished by accessing Extensions Manager either under the Apple menu in the Control Panels section or by double-clicking on Extensions Manager in the Control Panels folder (which is located in the System folder). Save the current set as “Standard” set or another name of your choosing. Using the Manager, turn off any unnecessary extensions by clicking on the item (the check mark

next to the item disappears, indicating that it has been disabled). Save the set as Paparazzi!.

This will be the set that you will need to use every time you want to play Paparazzi!. To play Paparazzi! with this set, follow these steps:

- 1) Before running Paparazzi! run Extensions Manager and load the Paparazzi! set. (You should see that only the extensions that you chose in the above step have check marks next to them. If not, perform the above step again.)
 - 2) Quit out of Extensions Manager and restart your computer. This will enable the Paparazzi! extensions set
 - 3) Play Paparazzi!
 - 4) Once you are done playing Paparazzi!, run Extensions Manager and load the "Standard" set (or the name you chose).
 - 5) Quit out of Extensions Manager and restart your computer.
 - 6) Your system is now configured to run programs other than Paparazzi!.
- C. If, after performing all of these steps, you are still unable to obtain 4400K of available memory (RAM), try disabling all fonts and unnecessary sounds. In addition, you may try to allocate less memory for QuickTime overhead via the Get Info window (however, this may cause some problems to appear).

Troubleshooting

Problem: During installation, when I place the extensions in the System folder, the computer tells me that it couldn't put in "QuickTime™" because it is in use.

Solution: First, hit the Cancel button. Second, find out which version of QuickTime™ you have. Go into the Extensions folder (located in the System folder), select the QuickTime™ extension and Get Info on it (either by choosing the option Get Info under the File menu or by hitting the Command and letter "I" keys simultaneously). Do the same for the QuickTime™ extension on Disc One. If the version in your System folder is a more recent version, don't replace your QuickTime™. If it is the same version, determine which was modified more recently. (This information is in the same Get Info window.) If your version was modified more recently, you do not need to replace it. If not, you will need to replace your QuickTime™ extension with ours. This is accomplished in the following manner:

- A. Disable your current QuickTime™ extension. (Detailed instructions on disabling extensions are in step 6B in the *Tips for Running on the Macintosh* section.)
- B. Restart your computer (to disable your QuickTime™ extension)
- C. Place our QuickTime™ extension (found on Disc One) in the "Extensions" folder.
- D. Restart your computer (to enable our newer QuickTime™ extension).
- E. You may trash your older QuickTime™ extension.

Problem: During installation, I was asked if I should replace an extension that already exists.

Solution: First, hit the Cancel button. Second, find out which version of the extension you have. Go into the Extensions folder (in the System folder), select the extension and Get Info on it (either by choosing the option Get Info under the File menu or by hitting the Command and letter “I” keys simultaneously). Do the same for the extension on Disc One. If the one in your System folder is a more recent version, don’t replace it. If it is the same version, determine which was modified more recently. (This information is in the same Get Info window.) If your version was modified more recently, you do not need to replace it. If not, you will need to replace your extension with ours — select the more recent extension, drag it into your Extensions folder and hit the replace button when the computer asks you if it should replace your extension.

Problem: When I try to play Paparazzi!, the computer says that there is not enough memory available.

Solution: You need to make more memory available for Paparazzi!:

- **If you are playing on a 680x0 Mac** — First, click on the OK button. Second, see step 6 in the Tips for Running on the Macintosh section.
- **If you are playing on a PowerPC** — First, click on the OK button. Second, select the Paparazzi! icon and Get Info on it (either by choosing the option Get Info under the File menu or by hitting the Command and letter “I” keys simultaneously). Once in the Get Info window, click on the Locked square (the “X” should disappear indicating that it is

okay to change the numbers), change the number in the Minimum and Preferred size fields to 4096 and then lock the window by clicking on the Locked square. Close the Get Info window and now try playing Paparazzi!. If you are still experiencing memory problems, see step 6 in the *Tips for Running on the Macintosh* section.

Problem: There is no picture when I play video clips (only audio works).

Solution: You need to leave more memory for QuickTime™ overhead. This means that you will have to reduce the amount of memory that the system needs (see step 6 in the *Tips for Running on the Macintosh* section).

Problem: A system error appeared on the screen while I was playing the game.

Solution: The first thing to do is not panic! The game automatically saves your progress (your progress is saved every time you come back from a shoot). These errors do surface from time to time because each computer is configured differently and certain conflicts do arise. Just quit out of the program and restart your computer. Restart Paparazzi! and choose the persona you were playing. You'll be back where you left off.

Problem: The video is not very detailed.

Solution: Your monitor is probably set for 256 colors (8-bit). Just go into the Monitors control panel in the Control Panels section under the Apple Menu and change your colors to thousands (16-bit).

Problem: It seems as if my particular shot is not being taken when I press the button.

Solution: Not to worry, the shot that is in the camera when you press the button, not when you hear the shutter click, is the one that is developed in the darkroom.

Problem: I need space on my hard drive, but I don't want to get rid of Paparazzi!

Solution: Paparazzi! automatically saves your progress. It does this by making changes to the player text files which are located in the "MUSEWTHY" folder (they are named APLAYERx.TXT). These files (there are six of them; one for each player) are the only ones which you need to save. Place these in a different folder or on a floppy diskette. Now you can throw away your "MUSEWTHY" folder. When you install MUSEWTHY back on your hard drive (by following the instructions in the Installation section), select and drag your saved APLAYERx.TXT files into the "MUSEWTHY" folder. When the computer asks you if you should replace the ones already in the folder, hit the Replace button. You are ready to play Paparazzi! where you left off.

Problem: When I'm at the point in the game when I need to switch Discs, the CD will not eject when the game asks me to switch.

Solution: Your computer and its peripherals (CD-ROM drives, DAT drives, etc.) are being shared. You need to turn File Sharing OFF. This is accomplished by quitting out of Paparazzi! (your progress will be saved automatically), going into the Control Panels folder (located in the System folder)

and double-clicking on Sharing Setup. Under the File Sharing section, make sure File Sharing is OFF. If File Sharing is not OFF, hit the Stop button to turn it off. Play Paparazzi! — you'll be back where you left off.

Problem: It seems as if my video and audio are not synchronized.

Solution: There are several remedies:

- First, be sure your System software version is at least 7.1.2 (we have experienced some problems with lower versions).
- Second, make sure your computer is optimized for Paparazzi! Perform steps 1 thru 4 in the *Tips for Running on the Macintosh* section. Try playing Paparazzi!
- Third, if you are still experiencing these problems, perform step 6 in the *Tips for Running on the Macintosh* section.

Please refer to the **READ ME** file on Disc One for any updated information.

CUSTOMER SERVICE

If you have any comments, questions or suggestions about PAPERAZZI! or any other Activision product, you can contact us at **(310) 479-5644** between the hours of 9:00 a.m. and 5:00 p.m. (Pacific Time) Monday through Friday, with the exception of holidays, or contact a customer service representative through the following on-line services:

Activision BBS: (310) 479-1335

- Available 24 hours a day
- Up to 14,400 Baud
- Settings: 8 Bits, No Parity, 1 Stop Bit (8, N, 1)

CompuServe: 76004,2122 or [GO GAMEPUB] in the Game Publishers Forum B

Prodigy: ACT110B

GEnie: ACTIVISION

America OnLine: ACTIVISION or use keyword "ACTIVISION" to locate the Activision forum.

Internet: support@activision.com

World Wide Web: <http://www.activision.com>

For customer service in Europe refer to the Warranty section at the end of this manual.

HERE'S THE SCENARIO

You're a hotshot photographer fresh out of art school, drawn by a natural desire to be where the action is. You could make it in Tinseltown. All you have to do is point and shoot, right?

Too bad it's not that easy. Competition is fierce. As your finances dwindle you realize it takes more than just a camera and a good eye to survive in Tinseltown. It takes the stubbornness of a mule, the memory of an elephant and the attitude of a horse's ass.

Your goal in *Paparazzi! Tales of Tinseltown* is to earn money by finding choice photo opportunities and shooting candid pictures of all 24 of Tinseltown's celebrities, without going broke or getting run out of town. You have only two weeks to make it big...and only four chances per day to nail the big money shot. Remember, your integrity is important. People will treat you differently depending on what kind of person you are and you're gonna need all the friends you can get. If you're looking to damage your reputation just sell out to the highest bidder.

First Things First... Who are you?

You can choose from six different personalities. Or in true Tinseltown style, you can be all of them at once.



STALKING THE PREY WITH THE FABULOUS PALMINATOR 2000



back often so you'll know whose scandalous behavior has escaped you.

Here's your very own cellular cable TV. Surf the channels for the latest news, or pick up hot gossip on shows like A Steamy Affair and Wanda Barren's Undergarments of the Stars. There are clues a-plenty here, folks.

This seamless interface is your ticket to Tinseltown and all of its inhabitants. You'll be a paparazzi in no time with this baby.

Now Check out the Local Talent

Click through the Guide to meet your targets, all 24 of them. Check





The Palminator is a message center too, keeping track of video-phone calls from your agent and your competitors. Check in to get the latest blab.

Scoot over to the luxurious Grand Habernet Hotel, or her distant cousin, the Aroma Motel. Just click on the map and head to the beach, or visit the ultra-hip Club Lingo. Have a beer with friends at the Blue Fug, or get some advice at Cheever's Cameras. There's no constraint on where you can go in the game, but to win you'll have to be in the right place at the right time.



IT'S TIME TO GO ON STAR-SAFARI...

This is clutch time. Watch the action through your camera, shoot your best shot (you have two chances, Ace), then hit the Flee button to speedaddle back to your lab.

Let's see what you've got...



Watch your future as a paparazzi develop before your eyes. Choose the better of the two and take it to market.

It's BIG MONEY TIME

If you're lucky enough to grab a decent shot you can choose what slimy publication you'll sell out to. Remember your integrity and money will be affected by your choice. After you choose, you'll see how the magazine used, or misused, your shot. Congratulations!

There is an on-line help...if you're a real loser!



AH, IN TINSELTOWN AT LAST...

This is it! Palm trees, Porsches, and premieres. You jump off the train before it stops moving, anticipating your first cover photo of a real star. But before you can even get out of the station, a greasy hand grabs your arm.

"Hey there, kid... You got a dollar? Anything, kid. I need a jug of Cool Breeze to ease my worried mind."

You dip into your meager finances. It's worth a dollar to you to escape from the clutches of this foul-smelling bum.

"Thanks, pal. You're a saint among sinners. What's that you got there? Is that a zoom lens in your pocket or are you just happy to see me?"

Disgusted, you try to pull away from the toothless old man, but you can't seem to move under his baleful gaze.

"You wouldn't be one of them paparazzis, would you? Gonna seek fame and fortune with that camera? Give it up, kid. They'll eat you alive here. Hey, I was a paparazzi, too. Just look what they done to me, kid."

You try to avert your eyes from the old man's scarred visage.

"Broken!" The bum smashes his empty wine bottle on the sidewalk and clutches you by the collar. The stench of his words makes you dizzy. "You really wanna try and make it around here? Then read this, kid!"

The retired photographer shoves a thin, tattered tour guide in your face. Dumbfounded, you accept the gift as the old man limps off to the liquor store.

Star-Watching
In Tinseltown!



**A
CELEBRITY
SEEKER'S
FOUR
GUIDE**


WELCOME TO TINSELTOWN!

If you're looking to meet the **BIG STARS**, then this is the book for you! We'll tell you who to look for, and where to find them! The rest is up to you! If you're really lucky, you might get everyone's autograph! So pay close attention, starseekers!

WHAT YOU'LL FIND IN THIS GUIDE

Map of Tinseltown	27
Where to Go?	28
Who's Who in Tinseltown	30
Read All About It!	36
Star-Watcher's Tips	38
Credits	39

MAP OF TINSELTOWN



See the following pages for descriptions of these locations.

WHERE TO GO?

If you want to meet the stars, all you have to do is put yourself in their shoes. It's not as hard as you think! Remember, even though they're stars, they still go shopping, eat out and frequent bars just like you and me. Here are a few places you can rub elbows with the rich and famous:

1. **APPLEFJORD VILLAGE** — Tinseltown's premier outdoor mall features all the latest fashions. You can bet that stars are wearing these clothes! Stroll in comfort through the air-conditioned plazas. Have a seat at one of the cafés and watch the shoppers walk by. All major credit cards are accepted.
2. **THE BLUE FUG** — Take a look at the walls of this little bar and you'll see Tinseltown history played out in pictures. Not many celebrities go here, but it's a great collection of photos and memorabilia. Ask the bartender for a Blue Fug and you'll definitely see stars.
3. **CHEEVER'S CAMERAS** — No vacation would be complete without photos of your star-gazing efforts. Here's a conveniently located little store with a friendly staff ready to supply you with the film and batteries you need.
4. **GRAND HABERNET HOTEL** — Home away from home for any wealthy person visiting Tinseltown. The utmost in service and

comfort. No appointment has been left to chance at this famous establishment.

5. **TINSELTOWN MUNICIPAL COURTHOUSE** — What better time to ask a Tinseltown resident for an autograph than when he or she is going to court?
6. **FALLEN ARCHES COUNTRY CLUB** — This exclusive club is where the stars take their leisure. There's a beautiful 18-hole golf course, a full gymnasium with personal training and massages, swimming pools, tennis courts and a ballroom for special events.
7. **CLUB LINGO** — This is Boogie Wonderland! The place to see and be seen! You gotta dress cool to get in to this place, but many fans just hang out in front and watch the stars come and go. The hottest dancing and the driest martinis are inside.
8. **SIGISMUNDO'S** — This dimly lit underground grotto features the finest in Italian cuisine. This restaurant became popular with the Tinseltown crowd way back in the '30s.
9. **SOOP-R VAL-U LEED-R MAR-KIT** — Even the stars have to go grocery shopping! Bump carts where the elite buy their meat, or get a manicure while one of the oh-so-friendly clerks does your shopping for you!

10. **THE ROSY CONCH** — If you're "Born to be Wild," then here's the club for you! Where else can you get your Harley valet parked while you down a few shots of Jack Daniels? A lot of the hottest rock bands got their start playing the Rosy. Make a visit and soak up the atmosphere.
11. **ALLEY** — Be careful!
12. **AROMA MOTEL** — Distant cousin of the Grand Habernet Hotel. Its patrons like to be inconspicuous, if you know what I mean.
13. **WINSTON A. BIGWELL PARK** — Tinseltown boasts a spacious and scenic park, adjacent to beautiful Bigwell Lake. Sometimes stars will jog through in a strange and rare brush with the public.

Who's Who in Tinseltown?

(Celebrity listing also available by pressing the Guide Button on the Palminator 2000.)

Jackie Rae Gunn: Jackie is a well-loved former first lady. Her husband is dead now, the first ever to contract Alzheimer's while in office. During the last three years of President Gunn's term, Jackie Rae be

came his most influential adviser. She often consulted astrological charts and drew on the experiences of her past lives to help run the country.

Barry Begonia: Sports writers have called him "the greatest Frisbee golfer that ever lived." But Begonia has been arrested for betting on the outcome of his own wife's pregnancy, and the PGDA has permanently kicked him off the Seniors tour. He says he's changed his ways.

Andre MacConnor: This 20-year-old upstart has taken the tennis world by storm. His mediocre play and rugged good looks have landed him a number of lucrative sponsorships for everything from deodorants to cameras to tanning salons.

Okra Salad Raffle: Okra is a self-made billionaire, starting as a local talk show host and becoming the huge entertainment mogul that she is today. She really seems to have her finger on the pulse of the nation. To Okra, the best medicine is a sympathetic ear and a large viewing audience.

Flash Rock Man! Far and away, the most famous man in the world. Inventor of "Flash Time!" and the "Flamin' Foot Fandango." His picture is proudly displayed in more households than Chairman Mao's ever was.

Andy Warthog: The hippest of the neo-pseudo-post-avant garde deconstructionists, Warthog is a hit in artistic circles. His latest exhibition, "My Life as a Tuning Fork," an entirely empty art gallery, expresses the angst and nihilism of a generation that cares only for instant gratification.

Elizabeth Naylor: The tabloids are always interested in Liz. She hasn't acted much in recent years, but that does not dim her popularity. Several high-profile marriages and well-publicized friendships keep her in the inner circle of stars. It also fuels sales of her cologne and diet shake mixes.

Lhasa Apso: Another actress who hasn't held down a role in years. But she's still one of the social elite of Tinseltown. Over the past 40 years, she's had a few dozen marriages and almost as many facelifts. Her temper is legendary.

Maharishi Yogurt bin Daun Toodee River: The highly visible leader of the world's fastest growing religion, Edification, the Maharishi Yogurt preaches a strict yogurt diet, pacifism and celibacy. Through his doctrines, millions have learned to live full, happy lives without polluting or overpopulating the earth.

Princess Grizelda Marie: Grizelda came to Tinseltown to be where the action is, and the British press followed her. The black sheep of the

royal family, Grizelda's partying attitude has won the derision of her family. The Queen would ask her to relinquish her title, but it would only create more bad press.

The Virgin Mary: This sultry pop singer definitely falls short of her namesake in the chastity department. A shrewd businesswoman, she cultivates her bad reputation to sell more albums.

Sharon Cheralike: Sharon has the firmest fanny in showbiz. Did she earn it, or was it put there by crafty surgeons? Whatever the case may be, she is one of the hardest working actress/singer/aerobic instructor/infomercial spokespersons in Tinseltown. She leads a very private personal life.

Axle Griese: Axle is the lead bassist for the controversial metal band Sucking Chest Wound. He is in perpetual therapy for a variety of vices. Mr. Griese is generally lewd, obnoxious, unwashed, drunk, stoned and coked up. Girls love him.

Vincenzo Cosa Nostra: The last of the great singers. Whether he's belting out opera or scatting through show tunes, nobody does it like "Old Big Nose." He's still the richest man in show business. Maybe it's the way the sounds reverberate in his colossal proboscis. Maybe he's got connections. No one nose.

Candy Inez Baker: Often called just "Inez," Candy is the supermodel of the year. Her cheekbones grace the cover of every fashion magazine on the rack.

Rusk Limburger: The darling of the reactionary right, Limburger thinks the nation is being run into the ground by a bunch of godless communist babykilling environmentalist fruitcake hippies. Maybe so, but Rusk only does complaints, not solutions.

H. Allan Eagler: Eagler took the fall for the last presidential administration in the "Guns-for-Jellybeans" scandal. The discharged army colonel still maintains that he was just following orders. His role in the investigation made him a patriot in the eyes of many, and he is now a best-selling writer of spy novels. He might even run for mayor.

Rob Estesheen: A high-profile member of the so-called "Rat Pack," Rob is also the son of famous actor Charlie Diamond-Fillup. He seems to fit the bill for any role requiring a young, handsome hero. He shares his father's natural acting ability, as well as his taste for liquor.

Jucia Rogers: Jucia Rogers is a young beauty who makes millions off of an innocent smile. Seemingly shy and quiet in public, Jucia still can't make her mind up when it comes to men.

Shawn Pendleton: Movie star and former husband of The Virgin Mary, Pendleton's post-divorce antics are great fodder for the tabloids. But beware, Pendleton does not take a liking to people like you.

Katie Johnston: Young Katie captured the heart of America with her triumphant figure skating performance in the Winter Olympics, where she won 2 gold medals. The bright-eyed 16-year old even appeared on cereal boxes. Now she has moved to Tinseltown to continue her professional skating career.

Frederick "Fast Freddie" Fredericks: Freddie is a prominent senator who hobnobs with the elite of Tinseltown. He used to be an oil freighter captain, but he claims to have commanded battleships. He follows the party line of the Pork Barrel Party.

Dink Winkelstein: Dink has been the host of every game show for the past 30 years. His memory is starting to go, but everybody loves him too much to fire him.

READ ALL ABOUT IT!

Don't be uninformed! Check out these fine publications for more on Tinseltown's "in" crowd!

Nosy Neighbor: Catch up on the latest rumors with the world's cheapest newspaper!

The Tinseltown Tattler: A gossip tabloid focusing on the bedroom activities of the Tinseltown crowd.

A Steamy Affair: One of the pioneers of "Tabloid TV," the syndicated A Steamy Affair has some shocking exposés!

Teen Heat: This adolescent girl's magazine features kissable pin-ups and dream dates with Tinseltown's hunks, plus more news about stars in general.

Famous Faces: A lighthearted gossip magazine that is interested in just about anything involving famous people.

Playmates: Insightful and important interviews and articles for men on world affairs, music, politics, fashion and sports. Oh, and there are naked women in it too!

The Entertainer: A weekly entertainment magazine that features movie and pop music reviews, as well as features on all your favorite stars.

Vanities: Vanities is kind of like the Wall Street Journal of the entertainment industry. It is read by everyone in Tinseltown. A bad review or a scandalous revelation in here could ruin a star's career.

You and Me: A grocery store newsstand personalities magazine. Common articles include "Would You be Caught Dead in This?" and "The Divorce: My Side of the Story."

Other People: Another personalities and human interest magazine. Common articles include "The Worst Dressed of 1994" and "The Divorce: The Other Side of the Story."

Sty Magazine: A tongue-in-cheek humor and personalities magazine. They love to embarrass the social butterflies!

News Revue Weekly: Politics is essentially acting, right? The Revue will keep you up to date on the nation's (and Tinseltown's) political arena.

STAR WATCHER'S TIPS

Here are a few final hints on star-watching to help you out!

BRING EXTRA CASH

If you can afford to hang out at the more expensive clubs and stores, you have a much better chance of meeting stars. You might even have to, um, "persuade" people to let you into places.

BE OBSERVANT

You'll need to pay attention to everything you see and hear. If you're not in the right place at the right time, you'll miss your brush with greatness.

GO TO THE BLUE FUG AND CHEEVERS

If you're running out of leads on where to find stars, ask the experts first. Some of the city's finest photographers frequent these locations. Buy one a drink and you might get a tip.

CONSERVE YOUR FILM

Always keep an extra shot in reserve! You never know who you might see in Tinseltown!

BEWARE OF IMPOSTORS

Tinseltown is full of people who claim to be stars. Some of them are even professional impersonators.

CREDITS

Executive Producer	JIM FREEMAN
Producer	JIM FREEMAN
Producer (Activision)	BILL ANKER
Game Concept/Design	JASON ENGLISH, JIM FREEMAN
Script	JASON ENGLISH
Video Producer/Director	JOHN WESTON KELLY
Media Integration	DOYLE E. CALVERT
Production Manager	JOE T. MOSELEY
Director of Photography	JOHN WESTON KELLY
Graphics	DOYLE E. CALVERT, JASON ENGLISH, JIM FREEMAN, JOHN WESTON KELLY, JOE T. MOSELEY
Video Editing	JIM FREEMAN, JOHN WESTON KELLY
Audio	JASON ENGLISH
Music Composition	JASON ENGLISH
Music Performed Live By	JASON ENGLISH, JOE T. MOSELEY, (no MIDI %\$*#)
Creative Director	RON GOULD
Package Design	JONATHAN BROWN
Documentation Manager	MICHAEL RIVERA
Editor	VERONICA MILITO
Key Grip	MIKE SIMPSON
Set Design	WENDY RODGERS

Cast (in no particular order)

The Alien	THE ALIEN
Jackie Rae Gunn	VICTORIA MUELLER
Barry Begonia	JOHN PUDDINGTON
Andre MacConnor	JIM FREEMAN
Okra Salad Raffle	JEANINE ROGERS
Flash Rock Man!	JOHNNY WIMBREY
Andy Warthog	JOE T. MOSELEY
Elizabeth Naylor	JANEY MINICK
Lhasa Apso	MARY ALLEN
Maharishi Yogurt	JULIAN QUIROZ
Princess Grizelda Marie	LAURA MILLER
The Virgin Mary	MOLLY NORTON
Sharon Cheralike	JENA KIRKPATRICK
Axle Griese	JASON ENGLISH
Vincenzo Cosa Nostra	CARMEN PICARIELLO
Candy Inez Baker	STACEY WEBB
Rusk Limburger	TOM NAU
H. Allan Eagler	COREY SHEFFIELD
Rob Estesheen	ALAN DUNN
Jucia Rogers	ELLEN LOCY
Shawn Pendleton	JOHN WESTON KELLY
Katie Johnston	PHILLIPA "POPPY" HESS

Frederick Fredericks	CHAD MCKNIGHT
Dink Winkelstein	BOB LEONARD
Willits T. McGovern	DAN BURKARTH
Goldie Risenstein	MARINCA CALO-OY
Chuck Hunsucker	NATHAN AMONDSON
Phillip Andrew Andrews	ELIAS TAYLORSON
Mr. Cheevers	ALAN HOLMES
Wanda Barren	SUSAN LARGO
Tip Ribeye	ANDRÉ LARRY
Chip Dashing	MARK NUTTER
Smyrna Smokowlowicz	SANDY CRISTA
Kurt Loaded	ERIC HAYDEN
Mary Steamy	PATTY LEWIS
Vela Starbright	JACKIE EVANS
Dr. Jerry Mander	ISRAEL UNGER
Frisbee Golf Foe	JON DIDIER
George Spielman	JOE T. MOSELEY
Andre's Personal Assistant	CHRISTINA MCKAE
Eli Brown	TRAVIS DERI
Richard Simpson	ERIK VALCIK
Limo Driver	FRED HANSSON
Virgy's Boyfriend	ISRAEL UNGER
Cereal Eater	DEBRA PRALLE
Billy	JERAD VALCIK

Infomercial GirlJANE PIATT
 BartenderMIKE SIMPSON
 Rob's GirlfriendMELANIE DUNN
 Gun Thug #1CHRIS SMITH
 Gun Thug #2JASON VARIAN
 Mandolin GuyJASON ENGLISH
 PyreuxMIKE SIMPSON
 Tyrant LizardJOE T. MOSELEY
 DoormanRANDY NORMAN
 Becky Jo FredericksCARLA HARRELL
 BambiTHERESA PETTS
 TrixieYVETTE GONZALES
 Helen HighwaterDIANE BRANNON
 MomCHRISTINE ENGLISH
 LandlordTOM ENGLISH
 and featuring SKIPPY as SKIPPY

Universal Voiceover Guy...ALAN HOLMES

Filmed Entirely In and Around Dallas
 In the Republic of Texas

Special Thanks to The Management and Staff of These Locations:

Addison Health Systems • Addison Theater Center • Chase Oaks Golf Club
 Cheval Equestrian Center • Club Clearview • Greenville Bar & Grill • July Alley

MoMo's Italian Restaurant • Park Cities Personal Training • The Stoneleigh Hotel
Travis Walk Unicam • Whole Foods Market • Denise Hitchcock

Location CoordinationJOHN KELLY, JIM FREEMAN

Music Recorded at Hai-Tex Studios, Dallas, Texas
Engineered by Mark Elliott

Casting by Museworthy, Inc.

Thanks to These Talent Agencies:

Peggy Taylor • Mary Collins • Kim Dawson
As well as the Brave Freelance Talent

MakeupPENNY SADLER

Sound EffectsJASON ENGLISH, JOE T. MOSELEY

Creative Script ConsultationJIM FREEMAN,
JOE T. MOSELEY, MIKE SIMPSON

Production AssistantsJASON VARIAN, CHRISTINA MCKAE

Legal AssistanceSHARON FJORDBAK

Quality AssuranceJASON VARIAN, MIKE SIMPSON, LANIER
JAMESON, COREY MCKENZIE, THE MUSEMEN

Activision Quality Assurance

Director, Quality Assurance & Customer Service JON DOELLSTEDT
Manager, Quality Assurance DAVE ARNSPIGER
QA Lead Tester (Windows) PETER BLUMEL
QA Lead Tester (Macintosh) MURALI TEGULAPALLE
Testers JUDITH CHLIPALA, ABE HEWARD

Made with Macromedia and QuickTime 2.0

Before You Look Past This Page!

1. Have you taken notes?
2. Have you consistently visited Cheevers during the day?
3. Have you been hanging out at the Blue Fug at night?

Once you look inside you can never say you did it all by yourself!

H. Allen Eagler

Listen to your friend.

Andre MacConner

Cheevers knows when a tennis shoe commercial will be shot.

Maharishi Yogurt

A pound of round Burger Brown can only be found at Appleford Village Mall.

Katie Johnston

Listen to who she thinks is cute and find out where he likes to hang out.

Frederick Fredericks

Willits has info but no insight.

Princess Grizelda

She has a regular workout schedule.

Rusk Limburger

Chuck knows where the Dominatrixes are — and so does Rusk.

The Alien

Cheever's has never seen him but The Alien knows Cheever's Cameras well.

Jackie Rae Gunn

Goldie has a clue on a potential rendezvous — and when Jackie's friend is in town the whole city hears about it.

Jucia Rogers

Goldie knows when Spielman will shoot Pure Heat's courtroom scenes.

Vincenzo Cosa Nostra

Giuseppe regularly cooks something special for Vincenzo.

Flash Rock Man!

Find kids, find shoes, find Flash.

Sharon Cheralike

Determine when she can get her hands on her Hair Tonic's special ingredient and watch her get her hands on something else.

Lhasa Apso

The Park's scenic path is the preferred pit stop for many pets.

Shawn Pendleton

Catch him with his hands full.

Liz Naylor

Run into George Spielman at Cheever's and think of where Liz may go for understanding.

Candy Inez Baker

Keep an eye open for specials - watch EVERY ad carefully.

Okra Salad Raffle

She likes to link show topics with locations.

Andy Warthog

For ten less three and plus one more, Home is three of ten less four.

Nomad kings and queens alight

Their burden'd crowns on down for night...

I am full of woe, it's pre-ordain'd

This night is borne of birthright stain'd.

Saharan crawler under dune
Will needle thread by light of moon...

Streak the dust from embers burn'd
Before the darken'd sky has turn'd.

Rob Estesheen

Willits couldn't catch up with him but you can.

Barry Begonia

I'll bet Tip's Tips get you there.

Axle Griese

Maybe it's the darkness that frustrates Axle's attempts.

Dink Winkelstein

Those relationships with co-workers can kill, especially when jealous lovers find out.

Virgin Mary

Rusk knows where, Fredericks knows when, but The Virgin doesn't know how to stop.

ACTIVISION Limited 90-Day Warranty

Activision warrants to the original consumer purchaser of this computer software product that the recording medium on which the software program is recorded will be free from defects in material and workmanship for 90 days from the date of purchase. If the recording medium is found defective within 90 days of original purchase, ACTIVISION agrees to replace, free of charge, any product discovered to be defective within such period upon receipt at its Factory Service Center of the product, postage paid, with proof of date of purchase, as long as the program is still being manufactured by ACTIVISION. In the event that the program is no longer available, ACTIVISION retains the right to substitute a similar product of equal or greater value.

This warranty is limited to the recording medium containing the software program originally provided by ACTIVISION and is not applicable to normal wear and tear. This warranty shall not be applicable and shall be void if the defect has arisen through abuse, mistreatment, or neglect. Any implied warranties applicable to this product are limited to the 90-day period described above. To receive a replacement, you should enclose the original product discs only, in protective packaging accompanied by:

- a brief statement describing the defect,
- your name and return address, and
- a photocopy of your dated sales receipt.

Please see the special "RETURNS" information for further instructions. Any questions? Call ACTIVISION Customer Support at one of the numbers shown below.

EXCEPT AS SET FORTH ABOVE, THIS WARRANTY IS IN LIEU OF ALL OTHER WARRANTIES, WHETHER ORAL OR WRITTEN, EXPRESS OR IMPLIED, INCLUDING ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE, AND NO OTHER REPRESENTATION OR CLAIMS OF ANY KIND SHALL BE BINDING ON OR OBLIGATE ACTIVISION. IN NO EVENT WILL ACTIVISION BE LIABLE FOR SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGE RESULTING FROM POSSESSION, USE, OR MALFUNCTION OF THIS PRODUCT, INCLUDING DAMAGE TO PROPERTY AND, TO THE EXTENT PERMITTED BY LAW, DAMAGES FOR PERSONAL INJURY, EVEN IF ACTIVISION HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. SOME STATES DO NOT ALLOW LIMITATIONS ON HOW LONG AN IMPLIED WARRANTY LASTS AND/OR THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE LIMITATIONS AND/OR EXCLUSION OR LIMITATION OF LIABILITY MAY NOT APPLY TO YOU. THIS WARRANTY GIVES YOU SPECIFIC LEGAL RIGHTS, AND YOU MAY HAVE OTHER RIGHTS WHICH VARY FROM STATE TO STATE.

After the warranty period, a defective Activision CD or floppy disk may be returned to Activision with a check or money order for \$7 U.S. (AUD\$12.00 for Australia, or £7.00 for Europe) currency per CD or floppy disk for replacement (must be within one year of purchase).

RETURNS: Certified mail is recommended for returns. For best service, please be sure to:

1. Send the original product discs only, in protective packaging.
2. Enclose a photocopy of your dated sales receipt.
3. Enclose your name and return address, typed or printed clearly, inside the package.
4. Enclose a brief note describing the problem(s) you have encountered with the software with the name of the product and the brand and model name or model number of your computer.

In the U.S. send to:
WARRANTY REPLACEMENTS
ACTIVISION
P.O. Box 67713
Los Angeles, CA 90067
USA
(310) 479-5644

In Europe send to:
WARRANTY REPLACEMENTS
ACTIVISION
Long Island House, 3A
1/4 Warple Way
London, W3 0RQ
United Kingdom
Disc Replacement: 0181 742 9400
Technical Support: 0990 111 557

In Australia send to:
WARRANTY REPLACEMENTS
ACTIVISION
P.O. Box 873
Epping, NSW 2121
Australia
(61) 2 869 0955

COPYRIGHT:

The enclosed software product is copyrighted and all rights are reserved by Museworthy, Inc. The product is published and distributed exclusively by Activision, Inc. The distribution of this product is intended for the use of the original purchaser only and for use only on the computer system specified. Lawful users of this program are hereby licensed only to read the program from its medium into memory of a computer solely for the purpose of executing the program. Copying (except for one backup copy on those systems which provide for it), duplicating, selling, or otherwise distributing this product is a violation of the law. This manual and all other documentation contained herein are copyrighted and all rights reserved by Activision, Inc. These documents may not, in whole or in part, be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine-readable form without prior consent, in writing, from Activision. Willful violations of the Copyright Law of the United States can result in civil damages of up to \$50,000 in addition to actual damages, plus criminal penalties of up to one year imprisonment and/or a \$10,000 fine. In addition, violations of the Copyright law of other jurisdictions may result in civil damages and, in certain circumstances, criminal penalties.

Printed in the U.S.A.

EXTRA! EXTRA!

EXCLUSIVE

paparazzi!

Tales of TinSeltown

ANDAL! SHOCK!

"He has
a
strong

"He flew
into a
rage
after
the
party"



ACTIVISION®